



Revision: A

chroma+scan 24x0 Release Notes Version 5.4.6.1

Compatibility Overview:

5.4.5.x	Sensor firmware 5.4.6.1 can be used in conjunction with stations and sensors running 5.4.5.x software.
5.4.6.x	Release 5.4.6.1 addresses the incompatibility between 5.4.6.x and 5.4.5.x software. For this reason it is not compatible with the 5.4.6.0 release.

Fixes:

<i>Drop in compatibility with 5.4.5.x software</i>	Addresses previous releases incompatibility with 5.4.5.x software.
<i>Fixes rare imager initialization issue</i>	In previous releases, a bug would result in sensor occasionally starting up with corrupted images that would appear fully saturated. This issue has been fixed.

